

# Basic Detail Report

## Title Side Chair

Date 1780-1800

Medium Cherry, hard maple, brass hardware, yellow moreen wool

Description Cherry side chair in the Chippendale, or rococo, style, with a scalloped crest rail, a pierced vase-shaped splat, straight front legs, and over-the-rails upholstery. The back of the chair is formed by a crest rail atop two stiles. The crest rail has an arched section in the center, both at the top and bottom edge, flanked by a cyma curved, or S-curved, section, and a fluted ear at each end. Centered below the crest rail is a flat, pierced, vase-shaped splat, with interlocking ribbons of wood creating a symmetrical pattern of C-scrolls and elongated openings. The splat is joined at the bottom to a tapered splat shoe, just above the back seat rail. Above the seat, each stile is slanted back. Below the seat, each stile forms a back leg which is slanted back, over a backward-slanting foot. The lower legs are slanted toward the center back of the chair. The seat is trapezoidal, with over-the-rails yellow moreen wool upholstery (replaced). The upholstery is secured with a straight line of brass nails along the bottom front edge of each seat rail. The front legs are straight; they extend from the height of the seat down to a plain foot. Both sides and the back of the chair each have a plain, rectangular stretcher connecting the legs. A medial stretcher connects the two side stretchers. Condition: The upholstery and brass nails are replaced; the brass nails follow the original pattern of nail holes. The interior upper edge of the back seat rail is repaired. The finish is restored. Design and

# Basic Detail Report

Construction Details: The crest rail is supported on a tenon at the top of each

stile; each of these joints is secured with a wooden pin. Above the seat, the back

of each stile is rounded. The splat is tenoned into the crest rail above and into

the back seat rail below. The splat shoe is nailed down onto the back seat rail; it

has a cut-out in the back to accommodate the bottom of the splat. Each seat rail

is tenoned into the top of the legs. The back and side stretchers are each

tenoned into the lower portion of the legs. The medial stretcher is dovetailed

into the side seat rails. The interior corner of each leg is canted. Upholstery

(replaced). The chair is upholstered with yellow moreen wool that is held in

place over the rails with a single row of brass nails (replaced) at the lower front

edge of the front and side seat rails; the replacement nails follow the original

nail holes. Additional tacks that hold the upholstery in place are located on the

underside of the front and side seat rails. Below the yellow wool is stuffing,

sackcloth, and canvas webbing.

Dimensions Primary Dimensions (overall height x width x depth): 38 15/16 x 20 7

/8 x 18 13/16in. (98.9 x 53 x 47.8cm)